

LiveCode 7.1.0 Release Notes

Table of contents

- Overview
- Known issues
- Platform support
 - Windows
 - Linux
 - Mac
- Setup
 - Installation
 - Uninstallation
- Reporting installer issues
- Activation
- Multi-user and network install support (4.5.3)
- Command-line installation
- Command-line activation
- Engine changes
 - mobileLaunchData function
 - Available information
 - the `*commandName*` and the `*commandArguments*`
 - Multimedia on MacOS with AVFoundation
 - Mobile Sockets
 - Objects are only deleted on idle
 - Specific bug fixes (7.1.0)
 - Specific bug fixes (7.1.0-rc-3)
 - Specific bug fixes (7.1.0-rc-2)
 - Specific bug fixes (7.1.0-rc-1)
 - Specific bug fixes (7.1.0-dp-1_release)
 - Specific bug fixes (7.1.0-dp-1)
- IDE changes
 - Specific bug fixes (7.1.0-rc-2)
 - Specific bug fixes (7.1.0-dp-1)
- LiveCode Builder changes
- Previous Release Notes

Overview

The LiveCode engine has undergone a large quantity of changes for the 7.0 release. The way values of variables are stored internally has been changed - in particular where before the engine used C-strings, it now uses a reference counted MCStringRef type. Every bit of code that displays text in LiveCode has been updated, and all the platform-specific API functions that manipulate characters now use the Unicode versions; as a result LiveCode is now fully Unicode compatible.

The implementation of Unicode compatibility necessitated a change to the stack file format, which means stacks saved in 7.0 format are not compatible with earlier versions of LiveCode. However you can still save stacks in legacy formats using the dropdown menu in the Save As... dialog.

The other significant change to engine internals is the work done on syntax refactoring. The code that deals with statement execution, function evaluation and property access has been cleaned up and separated out from the parsing code, and moved into distinct modules based on functionality. This represents a major first step towards being able to implement Open Language.

Known issues

Every effort has been made to ensure that externally, the engine behaviour is identical to the current unrefactored release. In other words, users should not notice any difference in functionality in their existing stacks.

- The installer will currently fail if you run it from a network share on Windows. Please copy the installer to a local disk before launching on this platform.
- The engine files are much larger than previous versions due to inclusion of ICU data

Platform support

The engine supports a variety of operating systems and versions. This section describes the platforms that we ensure the engine runs on without issue (although in some cases with reduced functionality).

Windows

The engine supports the following Windows OSes:

- Windows XP SP2 and above
- Windows Server 2003
- Windows Vista SP1 and above (both 32-bit and 64-bit)
- Windows 7 (both 32-bit and 64-bit)
- Windows Server 2008
- Windows 8.x (Desktop)

Note: On 64-bit platforms the engine still runs as a 32-bit application through the WoW layer.

Linux

The linux engine requires the following:

- Supported architectures:

32-bit or 64-bit Intel/AMD or compatible processor

32-bit ARMv6 with hardware floating-point (e.g. RaspberryPi)

- Common requirements for GUI functionality:

GTK/GDK/Glib 2.24 or later

Pango with Xft support

(optional) *esd* - required for audio output

(optional) *mplayer* - required for media player functionality

(optional) *lcms* - required for color profile support in images

(optional) *gksu* - required for privilege elevation support

- Requirements for 32-bit Intel/AMD:

glibc 2.3.6 or later

- Requirements for 64-bit Intel/AMD:

glibc 2.15 or later

- Requirements for ARMv6:

glibc 2.7 or later

Note: The GUI requirements are also required by Firefox and Chrome, so if your Linux distribution runs one of those, it will run the engine.

Note: If the optional requirements are not present then the engine will still run but the specified features will be disabled.

Note: It may be possible to compile and run LiveCode Community on other architectures but this is not officially supported.

Mac

The Mac engine supports:

- 10.6.x (Snow Leopard) on Intel
- 10.7.x (Lion) on Intel
- 10.8.x (Mountain Lion) on Intel
- 10.9.x (Mavericks) on Intel

Note: The engine runs as a 32-bit application regardless of the capabilities of the underlying processor.

Setup

Installation

Each distinct version has its own complete folder – multiple versions will no longer install side-by-side: on Windows (and Linux), each distinct version will gain its own start menu (application menu) entry; on Mac, each distinct version will have its own app bundle.

The default location for the install on the different platforms when installing for 'all users' are:

- Windows: <x86 program files folder>/RunRev/ LiveCode 7.1.0
- Linux: /opt/runrev/livecode-7.1.0
- Mac: /Applications/ LiveCode 7.1.0.app

The default location for the install on the different platforms when installing for 'this user' are:

- Windows: <user roaming app data folder>/RunRev/Components/LiveCode 7.1.0
- Linux: ~/.runrev/components/livecode-7.1.0
- Mac: ~/Applications/ LiveCode 7.1.0.app

Note: *If your linux distribution does not have the necessary support for authentication (gksu) then the installer will run without admin privileges so you will have to manually run it from an admin account to install into a privileged location.*

Uninstallation

On Windows, the installer hooks into the standard Windows uninstall mechanism. This is accessible from the appropriate pane in the control panel.

On Mac, simply drag the app bundle to the Trash.

On Linux, the situation is currently less than ideal:

- open a terminal
- `cd` to the folder containing your rev install. e.g.

```
cd /opt/runrev/livecode-7.1.0
```

- execute the `.setup.x86` file. i.e.

```
./setup.x86
```

- follow the on-screen instructions.

Reporting installer issues

If you find that the installer fails to work for you then please file a bug report in the RQCC or email support@runrev.com so we can look into the problem.

In the case of failed install it is vitally important that you include the following information:

- Your platform and operating system version
- The location of your home/user folder
- The type of user account you are using (guest, restricted, admin etc.)
- The installer log file located as follows:
 - **Windows 2000/XP:** <documents and settings folder>/<user>/Local Settings/

- **Windows Vista/7:** <users folder>/<user>/AppData/Local/RunRev/Logs
- **Linux:** <home>/runrev/logs
- **Mac:** <home>/Library/Application Support/Logs/RunRev

Activation

The licensing system ties your product licenses to a customer account system, meaning that you no longer have to worry about finding a license key after installing a new copy of LiveCode. Instead, you simply have to enter your email address and password that has been registered with our customer account system and your license key will be retrieved automatically.

Alternatively it is possible to activate the product via the use of a specially encrypted license file. These will be available for download from the customer center after logging into your account. This method will allow the product to be installed on machines that do not have access to the internet.

Multi-user and network install support (4.5.3)

In order to better support institutions needing to both deploy the IDE to many machines and to license them for all users on a given machine, a number of facilities have been added which are accessible by using the command-line.

Note: *These features are intended for use by IT administrators for the purposes of deploying LiveCode in multi-user situations. They are not supported for general use.*

Command-line installation

It is possible to invoke the installer from the command-line on both Mac and Windows. When invoked in this fashion, no GUI will be displayed, configuration being supplied by arguments passed to the installer.

On both platforms, the command is of the following form:

<exe> install noui *options*

Here *options* is optional and consists of one or more of the following:

-allusers	Install the IDE for all users. If not specified, the install will be done for the current user only.
-	
desktopshortcut	Place a shortcut on the Desktop (Windows-only)
-startmenu	Place shortcuts in the Start Menu (Windows-only)
-location	The location to install into. If not specified, the location defaults to those described in the <i>Layout</i> section above.
<i>location</i>	
-log <i>logfile</i>	A file to place a log of all actions in. If not specified, no log is generated.

Note that the command-line variant of the installer does not do any authentication. Thus, if you wish to install to an admin-only location you will need to be running as administrator before executing the command. As the installer is actually a GUI application, it needs to be run slightly differently from other command-line programs.

In what follows <installerexe> should be replaced with the path of the installer executable or app (inside the DMG) that has been downloaded.

On Windows, you need to do:

```
start /wait <installerexe> install noui options
```

On Mac, you need to do:

```
"<installerexe>/Contents/MacOS/installer" install noui options
```

On both platforms, the result of the installation will be written to the console.

Command-line activation

In a similar vein to installation, it is possible to activate an installation of LiveCode for all-users of that machine by using the command-line. When invoked in this fashion, no GUI will be displayed, activation being controlled by any arguments passed.

On both platforms, the command is of the form:

```
<exe> activate -file license -passphrase phrase
```

This command will load the manual activation file from *license*, decrypt it using the given *passphrase* and then install a license file for all users of the computer. Manual activation files can be downloaded from the 'My Products' section of the RunRev customer accounts area.

This action can be undone using the following command:

```
<exe> deactivate
```

Again, as the LiveCode executable is actually a GUI application it needs to be run slightly differently from other command-line programs.

In what follows <livecodeexe> should be replaced with the path to the installed LiveCode executable or app that has been previously installed.

On Windows, you need to do:

```
start /wait <livecodeexe> activate -file license -passphrase phrase
```

```
start /wait <livecodeexe> deactivate
```

On Mac, you need to do:

```
"<livecodeexe>/Contents/MacOS/LiveCode" activate -file license -passphrase phrase
```

```
"<livecodeexe>/Contents/MacOS/LiveCode" deactivate
```

On both platforms, the result of the activation will be written to the console.

Engine changes

mobileLaunchData function (7.1.0-rc-2)

This new function is available on Android and returns an array containing information from the Intent object used to launch the currently running app.

Available information

- `action` - The general action the app was launched to perform.
- `data` - The data to operate on.
- `type` - The MIME type of the data provided.
- `categories` - Additional information about the action to perform.
- `extras` - An array of action-specific data set by the calling activity.

the `commandName` and the `commandArguments` (7.1.0-rc-1)

The bugs [12106](#) and [12018](#) have been longstanding issues: `$0` is not the command name, but the first command argument (which does not follow the way Bash works).

To solve this issue and avoid breaking any script that uses the current way command arguments are retrieved with LiveCode (`$0` being the first commandline argument instead of the command name), we introduced two functions to allow the users to access the commandline name and arguments.

- the `commandName` returns the command that has been used to start the executable
- the `commandArguments` returns a 1-based, numeric array of the commandline arguments if no index is given. Returns the arguments at this index otherwise (or empty if the index is `< 1` or `>` number of parameters)

These functions are only implemented for desktop standalone applications and server scripts. They will return *empty* on mobile platforms and in the IDE.

Multimedia on MacOS with AVFoundation (7.1.0-dp-1)

What has changed?

The player object until now used QuickTime/QTKit APIs for audio and video playback. Since both QuickTime and QTKit have been deprecated by Apple, we have updated the player to use the new AVFoundation API. AVFoundation does not provide a controller for multimedia playback until OSX 10.9 and their new control bar is also missing some of the features provided by the QTKit controller, which required us to implement our own controller to ensure backward compatibility.

We have added three new properties to the player object enabling you to customise the appearance of the controller:

- The **hilitecolor** of a player is the color of the played area, the colour of the volume area, as well as the background color of a controller button when it is pressed.
- The **forecolor** of a player is the color of the selected area. The selected area is the area between the selection handles.
- The **backcolor** of a player is the color of the controller icons (volume icon, play/pause icon, scrub back/scrub forward icon).

We have also added support for getting information about the download progress of a remote multimedia file:

- The **loadedtime** of a player is the time up to which the movie can be played. The download progress is also displayed on the controller well.

You can also query the **status** property of the player. This property can take either of the values:

- **loading** (for remote multimedia files)
- **playing**
- **paused**

A new message is added to the player:

- The **playRateChanged** message is sent to the player when the rate is changed by the rate scrollbar controller. To enable the rate scrollbar controller, hold shift + click on scrubForward/scrubBack buttons of the player controller.

Note AVFoundation player is supported in OSX 10.8 and above. On systems running OSX 10.6 and 10.7, LiveCode continues to provide player functionality using the QTKit API.

Mobile Sockets (7.1.0-dp-1)

Socket support has been added to the mobile platforms. The following syntax has been added to the iOS and Android engines.

Commands:

- accept
- open socket
- close socket
- read from socket
- write to socket
- secure socket

Functions:

- openSockets

Messages:

- socketClosed
- socketError
- socketTimeout

Properties:

- socketTimeoutInterval

If you are secure sockets, the SSL library must be included in your standalone. To do this for iOS, make sure the "Encryption" checkbox of "Basic Application Settings" section on the iOS screen of the Standalone Application Settings window is selected. To do this for Android, make sure the "SSL & Encryption" checkbox of "Basic Application Settings" section on the Android screen of the Standalone Application Settings window is selected.

Objects are only deleted on idle (7.1.0-dp-1)

The engine will now flush any recently deleted objects after each command as long as they were

created during the current event handling loop.

If an object is created during one event handling loop, and then deleted during another nested event handling loop it won't be flushed until control returns to the original event handling loop.

The upshot is that in tight loops, creating and deleting objects will result in objects being flushed immediately, reducing memory usage and making it easier to write object processing code which creates and deleted many objects.

Specific bug fixes (7.1.0)

(bug fixes specific to the current build are highlighted in bold, reverted bug fixes are stricken through)

- 15753 App crash during launch on iPad2 with iOS min version set to 5.1.1 (LiveCode 7.1 RC+DP)**

Specific bug fixes (7.1.0-rc-3)

- 15898 Building 32-bit slice only causes app to crash on iPad 1

Specific bug fixes (7.1.0-rc-2)

- 15764 Android mobileControlCreate "player" not working
- 15756 various codepoint and codeunit functionality broken in standalones
- 15743 iOS standalone engine do not build anymore in Debug mode
- 15738 The "My LiveCode/Plugins" folder isn't created by the IDE when updating the BAF
- 15723 Incorrect wording in Business edition activation screen
- 15719 An error in a preOpenStack script aborted openStack
- 15718 'SSL library not found' error thrown on iOS when using SSL & Encryption library
- 15705 strange flash occurring under iOS with visual effect push left/right
- 15703 iOS app saved with minimum version 8.4 won't install on a device running iOS 8.4
- 15685 Fix the path to the OSX standalone engine on Linux
- 15684 "extras" key in array returned with mobileGetLaunchData is empty
- 15676 Unicode chars in a script can make the Script Editor crash on script opening

Specific bug fixes (7.1.0-rc-1)

- 15700 iOS sockets only accept a single connection
- 15692 [Docs] Dictionary entry for "flip" command is missing text
- 15675 IDE crashes on startup if DataTree is installed
- 15654 LiveCode 6.7.7 RC 1 / 7.1.0 DP 1 won't install on 10.6.8
- 15648 Exporting text to RTF text generates invalid output if there is the backgroundColor has been changed
- 15646 Memory leak when using 'put into of '
- 15642 revZip fails to open archive in 64-bit iOS
- 15633 ceiling (*ceil)* synonym is missing from the dictionary
- 15625 "record sound" is not replacing existing sound file
- 15623 machine() returns "unknown" in LiveCode 7.x on OSX
- 15619 Opening sqlite on iOS return "revdberror"
- 15602 Recursionlimit property cannot be set by script > 65535
- 15597 LiveCode 7 fail to export valid RTF text if lists are used

- 15592 memory leak in shell() on Mac
- 15590 Crop image within a repeat loop causes crash to desktop after a few iterations
- 15514 Blocking socket syntax now works in LiveCode Server.
- 15379 Regular Expression with binary input fails in LC 7
- 15200 Default cursor doesn't reset when set to empty
- 15096 Escape key does not dismiss the 'answer color' dialog
- 13923 formattedHeight of a button is incorrect if button has an icon
- 13575 Dictionary - iPhoneSetKeyboardReturnKey examples
- 12108 Better argument handling for livecode server scripts
- 11569 Scrolling a group crashes LiveCode when hiding scrollbar
- 7217 selectionChanged not sent on arrow navigation

Specific bug fixes (7.1.0-dp-1_release)

- 15572 French application menu is not translated.
- 11866 iPhoneHeadingCalibrationTimeout returns empty

Specific bug fixes (7.1.0-dp-1)

- 15577 Execution error caused when trying to set the "visited" property of a text link
- 15571 textEncode crashes with encoding UTF-32
- 15570 Do not run "after" handlers if an error occurs.
- 15569 Referenced jpg crashes application on Linux
- 15568 Crash if SSL lib can't load properly - ARTS
- 15566 Preferences Mobile Support can't find the SDK for Xcode 6.4
- 15561 Tooltip appears for controls out of the visible window
- 15556 Mouse focus not synced when object is created
- 15511 Erroneous assertion failure logged on server when doing 'go stack'
- 15508 Allow debug mode standalone engines to load script-only TEST_STACKS
- 15507 The filename / effective filename of the root script returns empty in LiveCode server.
- 15495 [Player] Progress Bar does not update when playing audio files and alwaysBuffer is true
- 15494 mobileControlGet ID
- 15472 Invisible player appears and causes LC to hang
- 15457 Repeat for each element subtly different in 7.0
- 15439 enabledTracks "can't set this property" in LC 7
- 15321 "record sound" is not creating a file in LC7 (Windows)
- 15263 Large files can EOF prematurely on Linux.
- 15259 DataGrid library missing in standalones
- 15191 Windows - Hiding a player in Run mode does not update the screen
- 14418 Player doesn't accept filenames starting with file://
- 14289 Update SQLite to 3.8.10.2
- 14056 Cannot hide cursor on Mac from LiveCode 6.7
- 13391 [[Player]] Make default foregroundColor a colour other than black
- 13390 [[Player]] foregroundColor and hiliteColor not saved with stack
- 13262 [[Player]] player object in hidden group still displays video image
- 12834 [[Player]] enhancement set colour of player controller buttons using backcolor property
- 11803 set the RTFText of field does not work on Android

- 6791 Objects are only deleted on idle
- 5209 FormattedHeight does not take into account controller
- 4123 eraser tool in magnify palette is 1 pixel off

IDE changes

Specific bug fixes (7.1.0-rc-2)

- 15723 Incorrect wording in Business edition activation screen
- 15717 iOS Version resets to 5.1.1

Specific bug fixes (7.1.0-dp-1)

- 15580 Mobile Support JDK path not updated after changing it
- 15545 Setting spaceAbove or spaceBelow on the first line of a table breaks it
- 15535 Magnify palette cannot be used in a standalone
- 15522 position of cell editing field in basic table field
- 15515 Find and replace does not support arrow keys
- 15510 Project Browser forces the unlocking of the cursor
- 15478 message box does not auto-scroll
- 6649 Editing a table field cell shows focus at the wrong place when margins are changed.

LiveCode Builder changes

Previous Release Notes

7.0.6 Release Notes	http://downloads.livecode.com/livecode/7_0_6/LiveCodeNotes-7_0_6.pdf
7.0.4 Release Notes	http://downloads.livecode.com/livecode/7_0_4/LiveCodeNotes-7_0_4.pdf
7.0.3 Release Notes	http://downloads.livecode.com/livecode/7_0_3/LiveCodeNotes-7_0_3.pdf
7.0.1 Release Notes	http://downloads.livecode.com/livecode/7_0_1/LiveCodeNotes-7_0_1.pdf
7.0.0 Release Notes	http://downloads.livecode.com/livecode/7_0_0/LiveCodeNotes-7_0_0.pdf
6.7.6 Release Notes	http://downloads.livecode.com/livecode/6_7_6/LiveCodeNotes-6_7_6.pdf
6.7.4 Release Notes	http://downloads.livecode.com/livecode/6_7_4/LiveCodeNotes-6_7_4.pdf
6.7.2 Release Notes	http://downloads.livecode.com/livecode/6_7_2/LiveCodeNotes-6_7_2.pdf
6.7.1 Release Notes	http://downloads.livecode.com/livecode/6_7_1/LiveCodeNotes-6_7_1.pdf
6.7.0 Release Notes	http://downloads.livecode.com/livecode/6_7_0/LiveCodeNotes-6_7_0.pdf
6.6.2 Release Notes	http://downloads.livecode.com/livecode/6_6_2/LiveCodeNotes-6_6_2.pdf
6.6.1 Release Notes	http://downloads.livecode.com/livecode/6_6_1/LiveCodeNotes-6_6_1.pdf
6.6.0 Release Notes	http://downloads.livecode.com/livecode/6_6_0/LiveCodeNotes-6_6_0.pdf
6.5.2 Release Notes	http://downloads.livecode.com/livecode/6_5_2/LiveCodeNotes-6_5_2.pdf
6.5.1 Release Notes	http://downloads.livecode.com/livecode/6_5_1/LiveCodeNotes-6_5_1.pdf
6.5.0 Release Notes	http://downloads.livecode.com/livecode/6_5_0/LiveCodeNotes-6_5_0.pdf
6.1.3 Release Notes	http://downloads.livecode.com/livecode/6_1_3/LiveCodeNotes-6_1_3.pdf
6.1.2 Release Notes	http://downloads.livecode.com/livecode/6_1_2/LiveCodeNotes-6_1_2.pdf
6.1.1 Release Notes	http://downloads.livecode.com/livecode/6_1_1/LiveCodeNotes-6_1_1.pdf
6.1.0 Release Notes	http://downloads.livecode.com/livecode/6_1_0/LiveCodeNotes-6_1_0.pdf